

If your kernel names your network interfaces ens192 or ens224 or anything else you dislike,  
You could do this to rename them:

1. Change the ifcfg file of the interface to the desired name  
Also change the reference in the file accordingly to the new name
  2. Get the mac address of the interface
  3. Add a line to /etc/udev/rules.d/70-persistent-ipoib.rules  
Only change the mac address, the original name and the desired name.
  4. reboot
1. 

```
cd /etc/sysconfig/network-scripts
mv ifcfg-ens192 ifcfg-eth0
sed -i s/ens192/eth0/ ifcfg-eth0
```
  2. 

```
ifconfig eth0 |grep ether|awk '{print $2}'
00:0c:29:46:d2:8a
```
  3. 

```
cd /etc/udev/rules.d/
vi 70-persistent-ipoib.rules
SUBSYSTEM=="net", ACTION=="add", DRIVERS=="?*", \
ATTR{address}=="00:0c:29:46:d2:8a", \
ATTR{type}=="1", KERNEL=="ens192", NAME="eth0"
```
  4. reboot